



Cabin Fever Quilts & LaRue's Country Quilts

• 435-257-0801 • www.aPatternGal.com


145 W. Main ~ Tremonton, UT 84337 Your Quilting Headquarters

© 9/2005, RaMel Enterprises, Inc. These instructions are for personal use only and are part of a kit. No part may be used for profit without prior written permission.

Hot Pad Quilt Blocks #11 Indiana Puzzle

General Piecing Rules For This Block Style:

- Sew and press seams away from the center.
- Sew scant $\frac{1}{4}$ " seam allowances, do not open seams.
- Strip sew, then cut into segments.
- Simple 9 patch



8.5" unfinished

Fabric Requirements

- A. Center Sq: $3 \frac{1}{8}" = 3 \frac{1}{2}"$ square
 B. Points: 2, $3 \frac{1}{2}"$ sq. = $3 \frac{1}{2}" \times 8"$
 C. Checkerboard corners: 8, $1 \frac{7}{8}"$ sq. = $4" \times 10"$
 D. Corners and edge: 2, $3 \frac{1}{2}"$ sq + 8, $1 \frac{7}{8}"$ sq = $4" \times 13"$

Quilt Block Outside Border to make a 10" square: 1.5" x 42"

Additional Hotpad Requirements: 1 fat 16th back fabric & 8.5" square batting.

Block Assembly:

Cutting:


1. Square up center to $3 \frac{1}{8}"$.
2. Cut 2, B&D $3 \frac{1}{2}"$ squares, set aside.
3. From C & D fabric, cut $1 \frac{7}{8}"$ strip from 4" segments.

Sewing:

1. Sew corner four patches first using CD fabric strips. Sew then cut apart into 8 segments $1 \frac{7}{8}"$ long. Flip one section and sew four patches.
2. Follow instructions on 2 part triangle squares and cut apart.
 - a. Cut and press 2 part triangle squares open.
3. Lay out block as shown above and sew rows together.
4. Press and square up block to 8.5"

METHODS

2 Part Triangle Squares. Draw diagonal line down the center of square. Draw two more lines $\frac{1}{4}"$ from the center line. Sew down outside lines and cut block apart down the center line after sewing.



3 Rows & 3 Columns. = Easiest to sew center row or column first sewing left and right blocks next to center as shown in diagrams. Next simply sew the corners onto the top and bottom or left and right columns. Now you have three rows or columns to sew together.

Sandwich, Pre-binding Hotpads. = Layer 100% Cotton W&N Batting square on bottom. Place back fabric face up onto batting, then place pieced block face down on top of back. Pin if needed and stitch around all four sides leaving a 2"-3" turning opening. Trim corners and turn right sides out. Then blind hem opening closed.